

# Using the Infinispan Command Line Interface

# Table of Contents

1. Getting Started with Infinispan CLI .....	2
1.1. Creating and modifying Infinispan users .....	2
1.1.1. Adding credentials .....	2
1.1.2. Assigning roles to users .....	3
1.1.3. Adding users to groups .....	3
1.1.4. User roles and permissions .....	4
1.2. Connecting to Infinispan Servers .....	5
1.3. Navigating CLI Resources .....	6
1.3.1. CLI Resources .....	7
1.4. Shutting down Infinispan Server .....	8
1.4.1. Infinispan cluster restarts .....	9
2. Performing Cache Operations with the Infinispan CLI .....	10
2.1. Creating remote caches with the Infinispan CLI .....	10
2.1.1. Cache configuration .....	10
2.2. Modifying Infinispan cache configuration .....	20
2.3. Adding Cache Entries .....	20
2.4. Clearing Caches and Deleting Entries .....	21
2.5. Deleting Caches .....	21
2.6. Configuring Automatic Cache Rebalancing .....	21
3. Performing Batch Operations .....	23
3.1. Performing Batch Operations with Files .....	23
3.2. Performing Batch Operations Interactively .....	23
4. Configuring the Infinispan CLI .....	25
4.1. Setting Infinispan CLI Properties and Persistent Storage .....	25
4.2. Creating Command Aliases .....	26
4.3. Trusting Infinispan Server Connections .....	26
4.4. Infinispan CLI Storage Directory .....	27
5. Working with Counters .....	28
5.1. Creating Counters .....	28
5.2. Adding Deltas to Counters .....	29
6. Performing Cross-Site Replication Operations .....	30
6.1. Bringing backup locations offline and online .....	30
6.2. Configuring cross-site state transfer modes .....	31
6.3. Pushing state to backup locations .....	31
7. Backing Up and Restoring Infinispan Clusters .....	32
7.1. Backing Up Infinispan Clusters .....	32
7.2. Restoring Infinispan Clusters from Backup Archives .....	33
8. Command Reference .....	35

8.1. ADD(1) .....	35
8.1.1. NAME .....	35
8.1.2. SYNOPSIS .....	35
8.1.3. OPTIONS .....	35
8.1.4. EXAMPLES .....	35
8.1.5. SEE ALSO .....	35
8.2. ALIAS(1) .....	35
8.2.1. NAME .....	35
8.2.2. SYNOPSIS .....	36
8.2.3. EXAMPLES .....	36
8.2.4. SEE ALSO .....	36
8.3. ALTER(1) .....	36
8.3.1. NAME .....	36
8.3.2. SYNOPSIS .....	36
8.3.3. ALTER CACHE OPTIONS .....	36
8.3.4. EXAMPLES .....	37
8.3.5. SEE ALSO .....	37
8.4. AVAILABILITY(1) .....	37
8.4.1. NAME .....	37
8.4.2. SYNOPSIS .....	37
8.4.3. OPTIONS .....	37
8.4.4. EXAMPLES .....	37
8.5. BACKUP(1) .....	37
8.5.1. NAME .....	37
8.5.2. SYNOPSIS .....	38
8.5.3. BACKUP CREATE OPTIONS .....	38
8.5.4. BACKUP GET OPTIONS .....	38
8.5.5. BACKUP RESTORE OPTIONS .....	38
8.5.6. EXAMPLES .....	39
8.5.7. SEE ALSO .....	40
8.6. BENCHMARK(1) .....	40
8.6.1. NAME .....	40
8.6.2. SYNOPSIS .....	40
8.6.3. BENCHMARK OPTIONS .....	40
8.6.4. EXAMPLES .....	41
8.7. CACHE(1) .....	41
8.7.1. NAME .....	41
8.7.2. SYNOPSIS .....	41
8.7.3. EXAMPLE .....	41
8.7.4. SEE ALSO .....	42
8.8. CAS(1) .....	42

8.8.1. NAME .....	42
8.8.2. SYNOPSIS .....	42
8.8.3. OPTIONS .....	42
8.8.4. EXAMPLE .....	42
8.8.5. SEE ALSO .....	42
8.9. CD(1) .....	42
8.9.1. NAME .....	42
8.9.2. DESCRIPTION .....	42
8.9.3. SYNOPSIS .....	42
8.9.4. EXAMPLE .....	43
8.9.5. SEE ALSO .....	43
8.10. CLEARCACHE(1) .....	43
8.10.1. NAME .....	43
8.10.2. SYNOPSIS .....	43
8.10.3. EXAMPLES .....	43
8.10.4. SEE ALSO .....	43
8.11. CONFIG(1) .....	43
8.11.1. NAME .....	43
8.11.2. SYNOPSIS .....	43
8.11.3. DESCRIPTION .....	43
8.11.4. COMMAND SYNOPSIS .....	44
8.11.5. COMMON OPTIONS .....	44
8.11.6. CONVERT OPTIONS .....	44
8.11.7. PROPERTIES .....	44
8.11.8. EXAMPLES .....	45
8.11.9. SEE ALSO .....	45
8.12. CONNECT(1) .....	45
8.12.1. NAME .....	45
8.12.2. DESCRIPTION .....	45
8.12.3. SYNOPSIS .....	45
8.12.4. OPTIONS .....	45
8.12.5. EXAMPLE .....	46
8.12.6. SEE ALSO .....	46
8.13. CONTAINER(1) .....	46
8.13.1. NAME .....	46
8.13.2. SYNOPSIS .....	46
8.13.3. EXAMPLE .....	46
8.13.4. SEE ALSO .....	46
8.14. COUNTER(1) .....	46
8.14.1. NAME .....	46
8.14.2. SYNOPSIS .....	46

8.14.3. EXAMPLE .....	46
8.14.4. SEE ALSO .....	47
8.15. CREATE(1) .....	47
8.15.1. NAME .....	47
8.15.2. SYNOPSIS .....	47
8.15.3. CREATE CACHE OPTIONS .....	47
8.15.4. CREATE COUNTER OPTIONS .....	47
8.15.5. EXAMPLES .....	48
8.15.6. SEE ALSO .....	48
8.16. CREDENTIALS(1) .....	48
8.16.1. NAME .....	48
8.16.2. SYNOPSIS .....	48
8.16.3. DESCRIPTION .....	48
8.16.4. SYNOPSIS .....	48
8.16.5. OPTIONS .....	48
8.16.6. CREDENTIALS ADD OPTIONS .....	49
8.16.7. EXAMPLES .....	49
8.17. DESCRIBE(1) .....	49
8.17.1. NAME .....	49
8.17.2. SYNOPSIS .....	49
8.17.3. EXAMPLES .....	50
8.17.4. SEE ALSO .....	50
8.18. DISCONNECT(1) .....	50
8.18.1. NAME .....	50
8.18.2. SYNOPSIS .....	50
8.18.3. EXAMPLE .....	50
8.18.4. SEE ALSO .....	50
8.19. DROP(1) .....	50
8.19.1. NAME .....	50
8.19.2. SYNOPSIS .....	50
8.19.3. EXAMPLES .....	51
8.19.4. SEE ALSO .....	51
8.20. ENCODING(1) .....	51
8.20.1. NAME .....	51
8.20.2. DESCRIPTION .....	51
8.20.3. SYNOPSIS .....	51
8.20.4. EXAMPLE .....	51
8.20.5. SEE ALSO .....	51
8.21. GET(1) .....	51
8.21.1. NAME .....	52
8.21.2. SYNOPSIS .....	52

8.21.3. OPTIONS .....	52
8.21.4. EXAMPLE .....	52
8.21.5. SEE ALSO .....	52
8.22. HELP(1) .....	52
8.22.1. NAME .....	52
8.22.2. SYNOPSIS .....	52
8.22.3. EXAMPLE .....	52
8.22.4. SEE ALSO .....	52
8.23. INSTALL(1) .....	52
8.23.1. NAME .....	52
8.23.2. DESCRIPTION .....	53
8.23.3. SYNOPSIS .....	53
8.23.4. ARTIFACT NAMES .....	53
8.23.5. CHECKSUM VALIDATION .....	53
8.23.6. PATCH LIST OPTIONS .....	53
8.23.7. EXAMPLES .....	54
8.24. LOGGING(1) .....	54
8.24.1. NAME .....	54
8.24.2. SYNOPSIS .....	54
8.24.3. LOGGING SET OPTIONS .....	54
8.24.4. EXAMPLES .....	55
8.25. LS(1) .....	55
8.25.1. NAME .....	55
8.25.2. SYNOPSIS .....	55
8.25.3. EXAMPLES .....	55
8.25.4. SEE ALSO .....	55
8.26. MIGRATE(1) .....	55
8.26.1. NAME .....	55
8.26.2. SYNOPSIS .....	55
8.26.3. DESCRIPTION .....	55
8.26.4. COMMAND SYNOPSIS .....	56
8.26.5. COMMON OPTIONS .....	56
8.26.6. CLUSTER CONNECTION OPTIONS .....	57
8.27. PATCH(1) .....	57
8.27.1. NAME .....	57
8.27.2. DESCRIPTION .....	57
8.27.3. SYNOPSIS .....	57
8.27.4. PATCH LIST OPTIONS .....	57
8.27.5. PATCH INSTALL OPTIONS .....	57
8.27.6. PATCH DESCRIBE OPTIONS .....	58
8.27.7. PATCH ROLLBACK OPTIONS .....	58

8.27.8. PATCH CREATE OPTIONS .....	58
8.27.9. EXAMPLES .....	58
8.28. PUT(1) .....	58
8.28.1. NAME .....	58
8.28.2. DESCRIPTION .....	58
8.28.3. SYNOPSIS .....	59
8.28.4. OPTIONS .....	59
8.28.5. EXAMPLES .....	59
8.28.6. SEE ALSO .....	59
8.29. QUERY(1) .....	59
8.29.1. NAME .....	59
8.29.2. SYNOPSIS .....	60
8.29.3. OPTIONS .....	60
8.29.4. EXAMPLES .....	60
8.29.5. SEE ALSO .....	60
8.30. QUIT(1) .....	60
8.30.1. NAME .....	60
8.30.2. SYNOPSIS .....	60
8.30.3. EXAMPLE .....	60
8.30.4. SEE ALSO .....	61
8.31. REBALANCE(1) .....	61
8.31.1. NAME .....	61
8.31.2. SYNOPSIS .....	61
8.31.3. EXAMPLES .....	61
8.32. REMOVE(1) .....	61
8.32.1. NAME .....	61
8.32.2. SYNOPSIS .....	61
8.32.3. OPTIONS .....	61
8.32.4. EXAMPLE .....	62
8.32.5. SEE ALSO .....	62
8.33. RESET(1) .....	62
8.33.1. NAME .....	62
8.33.2. SYNOPSIS .....	62
8.33.3. EXAMPLE .....	62
8.33.4. SEE ALSO .....	62
8.34. SCHEMA(1) .....	62
8.34.1. NAME .....	62
8.34.2. SYNOPSIS .....	62
8.34.3. OPTIONS .....	62
8.34.4. EXAMPLE .....	62
8.34.5. SEE ALSO .....	63

8.35. SERVER(1) .....	63
8.35.1. NAME .....	63
8.35.2. DESCRIPTION .....	63
8.35.3. SYNOPSIS .....	63
8.35.4. SERVER CONNECTOR IPFILTER OPTIONS .....	63
8.35.5. EXAMPLES .....	63
8.36. SHUTDOWN(1) .....	64
8.36.1. NAME .....	64
8.36.2. SYNOPSIS .....	64
8.36.3. EXAMPLES .....	64
8.36.4. SEE ALSO .....	65
8.37. SITE(1) .....	65
8.37.1. NAME .....	65
8.37.2. SYNOPSIS .....	65
8.37.3. OPTIONS .....	66
8.37.4. STATE TRANSFER MODE OPTIONS .....	66
8.37.5. EXAMPLES .....	66
8.38. STATS(1) .....	67
8.38.1. NAME .....	67
8.38.2. SYNOPSIS .....	67
8.38.3. EXAMPLES .....	67
8.38.4. SEE ALSO .....	67
8.39. TASK(1) .....	67
8.39.1. NAME .....	67
8.39.2. SYNOPSIS .....	67
8.39.3. EXAMPLES .....	68
8.39.4. OPTIONS .....	68
8.39.5. SEE ALSO .....	68
8.40. UNALIAS(1) .....	68
8.40.1. NAME .....	68
8.40.2. SYNOPSIS .....	68
8.40.3. EXAMPLES .....	68
8.40.4. SEE ALSO .....	68
8.41. USER(1) .....	68
8.41.1. NAME .....	68
8.41.2. SYNOPSIS .....	69
8.41.3. DESCRIPTION .....	69
8.41.4. COMMAND SYNOPSIS .....	69
8.41.5. COMMON OPTIONS .....	70
8.41.6. USER CREATE/MODIFY OPTIONS .....	70
8.41.7. USER LS OPTIONS .....	70



8.41.8. USER ENCRYPT-ALL OPTIONS .....	71
8.42. VERSION(1) .....	71
8.42.1. NAME .....	71
8.42.2. SYNOPSIS .....	71
8.42.3. EXAMPLE .....	71
8.42.4. SEE ALSO .....	71

Connect to Infinispan Server with the Command Line Interface (CLI) to access data and perform administrative operations such as creating users, installing dependencies, and more.

# Chapter 1. Getting Started with Infinispan CLI

The command line interface (CLI) lets you remotely connect to Infinispan Server to access data and perform administrative functions. Complete the following procedures to learn basic CLI usage such as creating users, connecting to Infinispan, and navigating resources.

## 1.1. Creating and modifying Infinispan users

Add Infinispan user credentials and assign permissions to control access to data.

Infinispan server installations use a property realm to authenticate users for the Hot Rod and REST endpoints. This means you need to create at least one user before you can access Infinispan.

By default, users also need roles with permissions to access caches and interact with Infinispan resources. You can assign roles to users individually or add users to groups that have role permissions.

You create users and assign roles with the `user` command in the Infinispan command line interface (CLI).



Run `help user` from a CLI session to get complete command details.

### 1.1.1. Adding credentials

You need an `admin` user for the Infinispan Console and full control over your Infinispan environment. For this reason you should create a user with `admin` permissions the first time you add credentials.

#### *Procedure*

1. Open a terminal in `$ISPN_HOME`.
2. Create an `admin` user with the `user create` command.
  - Add a user assigned to the `admin` group.

```
bin/cli.sh user create myuser -p changeme -g admin
```

- Use implicit authorization to gain `admin` permissions.

```
bin/cli.sh user create admin -p changeme
```

3. Open `user.properties` and `groups.properties` with any text editor to verify users and groups.

```
$ cat server/conf/users.properties

#$REALM_NAME=default$
#$ALGORITHM=encrypted$
myuser=scram-sha-1\:BYGcIAwvf6b...

$ cat server/conf/groups.properties

myuser=admin
```

### 1.1.2. Assigning roles to users

Assign roles to users so they have the correct permissions to access data and modify Infinispan resources.

#### *Procedure*

1. Start a CLI session with an **admin** user.

```
$ bin/cli.sh
```

2. Assign the **deployer** role to "katie".

```
[//containers/default]> user roles grant --roles=deployer katie
```

3. List roles for "katie".

```
[//containers/default]> user roles ls katie
["deployer"]
```

### 1.1.3. Adding users to groups

Groups let you change permissions for multiple users. You assign a role to a group and then add users to that group. Users inherit permissions from the group role.

#### *Procedure*

1. Start a CLI session with an **admin** user.
2. Use the **user create** command to create a group.
  - a. Specify "developers" as the group name with the **--groups** argument.
  - b. Set a username and password for the group.

In a property realm, a group is a special type of user that also requires a username and password.

```
[//containers/default]> user create --groups=developers developers -p changeme
```

3. List groups.

```
[//containers/default]> user ls --groups  
["developers"]
```

4. Assign the **application** role to the "developers" group.

```
[//containers/default]> user roles grant --roles=application developers
```

5. List roles for the "developers" group.

```
[//containers/default]> user roles ls developers  
["application"]
```

6. Add existing users, one at a time, to the group as required.

```
[//containers/default]> user groups john --groups=developers
```

### 1.1.4. User roles and permissions

Infinispan includes a default set of roles that grant users with permissions to access data and interact with Infinispan resources.

**ClusterRoleMapper** is the default mechanism that Infinispan uses to associate security principals to authorization roles.



**ClusterRoleMapper** matches principal names to role names. A user named **admin** gets **admin** permissions automatically, a user named **deployer** gets **deployer** permissions, and so on.

Role	Permissions	Description
<b>admin</b>	ALL	Superuser with all permissions including control of the Cache Manager lifecycle.
<b>deployer</b>	ALL_READ, ALL_WRITE, LISTEN, EXEC, MONITOR, CREATE	Can create and delete Infinispan resources in addition to <b>application</b> permissions.

Role	Permissions	Description
<code>application</code>	ALL_READ, ALL_WRITE, LISTEN, EXEC, MONITOR	Has read and write access to Infinispan resources in addition to <code>observer</code> permissions. Can also listen to events and execute server tasks and scripts.
<code>observer</code>	ALL_READ, MONITOR	Has read access to Infinispan resources in addition to <code>monitor</code> permissions.
<code>monitor</code>	MONITOR	Can view statistics via JMX and the <code>metrics</code> endpoint.

### Reference

- [org.infinispan.security.AuthorizationPermission Enumeration](https://www.infinispan.org/documentation/12.0/en/reference/authorization/permissions.html)
- [Infinispan configuration schema reference](https://www.infinispan.org/documentation/12.0/en/reference/configuration/schema.html)

## 1.2. Connecting to Infinispan Servers

Establish CLI connections to Infinispan.

### Prerequisites

Add user credentials and have at least one running Infinispan server instance.

### Procedure

1. Open a terminal in `$ISP_HOME`.
2. Start the CLI.

- **Linux:**

```
bin/cli.sh
```

- **Microsoft Windows:**

```
bin\cli.bat
```

3. Run the `connect` command and enter your username and password when prompted.
  - Infinispan Server on the default port of `11222`:

```
[disconnected]> connect
```

- Infinispan Server with a port offset of `100`:

```
[disconnected]> connect 127.0.0.1:11322
```

## 1.3. Navigating CLI Resources

The Infinispan CLI exposes a navigable tree that allows you to list, describe, and manipulate Infinispan cluster resources.



Press the tab key to display available commands and options. Use the **-h** option to display help text.

When you connect to a Infinispan cluster, it opens in the context of the default cache container.

```
[//containers/default]>
```

- Use **ls** to list resources.

```
[//containers/default]> ls  
caches  
counters  
configurations  
schemas  
tasks
```

- Use **cd** to navigate the resource tree.

```
cd caches
```

- Use **describe** to view information about resources.

```
describe
```

```
{
  "name" : "default",
  "version" : "xx.x.x-FINAL",
  "cluster_name" : "cluster",
  "coordinator" : true,
  "cache_configuration_names" : [ "org.infinispan.REPL_ASYNC",
  "___protobuf_metadata", "org.infinispan.DIST_SYNC", "org.infinispan.LOCAL",
  "org.infinispan.INVALIDATION_SYNC", "org.infinispan.REPL_SYNC",
  "org.infinispan.SCATTERED_SYNC", "org.infinispan.INVALIDATION_ASYNC",
  "org.infinispan.DIST_ASYNC" ],
  "physical_addresses" : "[192.0.2.0:7800]",
  "coordinator_address" : "<hostname>",
  "cache_manager_status" : "RUNNING",
  "created_cache_count" : "1",
  "running_cache_count" : "1",
  "node_address" : "<hostname>",
  "cluster_members" : [ "<hostname1>", "<hostname2>" ],
  "cluster_members_physical_addresses" : [ "192.0.2.0:7800", "192.0.2.0:7801" ],
  "cluster_size" : 2,
  "defined_caches" : [ {
    "name" : "mycache",
    "started" : true
  }, {
    "name" : "___protobuf_metadata",
    "started" : true
  } ]
}
```

### 1.3.1. CLI Resources

The Infinispan CLI exposes different resources to:

- create, modify, and manage local or clustered caches.
- perform administrative operations for Infinispan clusters.

#### Cache Resources

```
[//containers/default]> ls
caches
counters
configurations
schemas
```

#### caches

Infinispan cache instances. The default cache container is empty. Use the CLI to create caches from templates or `infinispan.xml` files.



### counters

**Strong** or **Weak** counters that record the count of objects.

### configurations

Infinispan configurations.

### schemas

Protocol Buffers (Protobuf) schemas that structure data in the cache.

### tasks

Remote tasks creating and managing Infinispan cache definitions.

### Cluster Resources

```
[hostname@cluster/]> ls
containers
cluster
server
```

### containers

Cache containers on the Infinispan cluster.

### cluster

Lists Infinispan servers joined to the cluster.

### server

Resources for managing and monitoring Infinispan servers.

## 1.4. Shutting down Infinispan Server

Stop individually running servers or bring down clusters gracefully.

### Procedure

1. Create a CLI connection to Infinispan.
2. Shut down Infinispan Server in one of the following ways:
  - Stop all nodes in a cluster with the **shutdown cluster** command, for example:

```
shutdown cluster
```

This command saves cluster state to the **data** folder for each node in the cluster. If you use a cache store, the **shutdown cluster** command also persists all data in the cache.

- Stop individual server instances with the **shutdown server** command and the server hostname, for example:

```
shutdown server <my_server01>
```



The `shutdown server` command does not wait for rebalancing operations to complete, which can lead to data loss if you specify multiple hostnames at the same time.



Run `help shutdown` for more details about using the command.

#### *Verification*

Infinispan logs the following messages when you shut down servers:

```
ISPN080002: Infinispan Server stopping
ISPN000080: Disconnecting JGroups channel cluster
ISPN000390: Persisted state, version=<$version> timestamp=YYYY-MM-DDTHH:MM:SS
ISPN080003: Infinispan Server stopped
```

### **1.4.1. Infinispan cluster restarts**

When you bring Infinispan clusters back online after shutting them down, you should wait for the cluster to be available before adding or removing nodes or modifying cluster state.

If you shutdown clustered nodes with the `shutdown server` command, you must restart each server in reverse order.

For example, if you shutdown `server1` and then shutdown `server2`, you should first start `server2` and then start `server1`.

If you shutdown a cluster with the `shutdown cluster` command, clusters become fully operational only after all nodes rejoin.

You can restart nodes in any order but the cluster remains in DEGRADED state until all nodes that were joined before shutdown are running.

# Chapter 2. Performing Cache Operations with the Infinispan CLI

Use the command line interface (CLI) to perform operations on remote caches such as creating caches, manipulating data, and rebalancing.

## 2.1. Creating remote caches with the Infinispan CLI

Use the Infinispan Command Line Interface (CLI) to add remote caches on Infinispan Server.

### Prerequisites

- Create a Infinispan user with **admin** permissions.
- Start at least one Infinispan Server instance.
- Have a Infinispan cache configuration.

### Procedure

1. Start the CLI and enter your credentials when prompted.

```
bin/cli.sh
```

2. Use the **create cache** command to create remote caches.

For example, create a cache named "mycache" from a file named **mycache.xml** as follows:

```
create cache --file=mycache.xml mycache
```

### Verification

1. List all remote caches with the **ls** command.

```
ls caches  
mycache
```

2. View cache configuration with the **describe** command.

```
describe caches/mycache
```

### 2.1.1. Cache configuration

You can create declarative cache configuration in XML, JSON, and YAML format.

All declarative caches must conform to the Infinispan schema. Configuration in JSON format must

follow the structure of an XML configuration, elements correspond to objects and attributes correspond to fields.



Infinispan restricts characters to a maximum of 255 for a cache name or a cache template name. If you exceed this character limit, the Infinispan server might abruptly stop without issuing an exception message. Write succinct cache names and cache template names.



A file system might set a limitation for the length of a file name, so ensure that a cache's name does not exceed this limitation. If a cache name exceeds a file system's naming limitation, general operations or initialing operations towards that cache might fail. Write succinct cache names and cache template names.

## Distributed caches

### XML

```
<distributed-cache owners="2"
    segments="256"
    capacity-factor="1.0"
    l1-lifespan="5000"
    mode="SYNC"
    statistics="true">
  <encoding media-type="application/x-protostream"/>
  <locking isolation="REPEATABLE_READ"/>
  <transaction mode="FULL_XA"
    locking="OPTIMISTIC"/>
  <expiration lifespan="5000"
    max-idle="1000" />
  <memory max-count="1000000"
    when-full="REMOVE"/>
  <indexing enabled="true"
    storage="local-heap">
    <index-reader refresh-interval="1000"/>
  </indexing>
  <partition-handling when-split="ALLOW_READ_WRITES"
    merge-policy="PREFERRED_NON_NULL"/>
  <persistence passivation="false">
    <!-- Persistent storage configuration. -->
  </persistence>
</distributed-cache>
```

```
{
  "distributed-cache": {
    "mode": "SYNC",
    "owners": "2",
    "segments": "256",
    "capacity-factor": "1.0",
    "l1-lifespan": "5000",
    "statistics": "true",
    "encoding": {
      "media-type": "application/x-protostream"
    },
    "locking": {
      "isolation": "REPEATABLE_READ"
    },
    "transaction": {
      "mode": "FULL_XA",
      "locking": "OPTIMISTIC"
    },
    "expiration" : {
      "lifespan" : "5000",
      "max-idle" : "1000"
    },
    "memory": {
      "max-count": "1000000",
      "when-full": "REMOVE"
    },
    "indexing" : {
      "enabled" : true,
      "storage" : "local-heap",
      "index-reader" : {
        "refresh-interval" : "1000"
      }
    },
    "partition-handling" : {
      "when-split" : "ALLOW_READ_WRITES",
      "merge-policy" : "PREFERRED_NON_NULL"
    },
    "persistence" : {
      "passivation" : false
    }
  }
}
```

```
distributedCache:
  mode: "SYNC"
  owners: "2"
  segments: "256"
  capacityFactor: "1.0"
  l1Lifespan: "5000"
  statistics: "true"
  encoding:
    mediaType: "application/x-protostream"
  locking:
    isolation: "REPEATABLE_READ"
  transaction:
    mode: "FULL_XA"
    locking: "OPTIMISTIC"
  expiration:
    lifespan: "5000"
    maxIdle: "1000"
  memory:
    maxCount: "1000000"
    whenFull: "REMOVE"
  indexing:
    enabled: "true"
    storage: "local-heap"
    indexReader:
      refreshInterval: "1000"
  partitionHandling:
    whenSplit: "ALLOW_READ_WRITES"
    mergePolicy: "PREFERRED_NON_NULL"
  persistence:
    passivation: "false"
    # Persistent storage configuration.
```

## Replicated caches

```
<replicated-cache segments="256"
    mode="SYNC"
    statistics="true">
  <encoding media-type="application/x-protostream"/>
  <locking isolation="REPEATABLE_READ"/>
  <transaction mode="FULL_XA"
    locking="OPTIMISTIC"/>
  <expiration lifespan="5000"
    max-idle="1000" />
  <memory max-count="1000000"
    when-full="REMOVE"/>
  <indexing enabled="true"
    storage="local-heap">
    <index-reader refresh-interval="1000"/>
  </indexing>
  <partition-handling when-split="ALLOW_READ_WRITES"
    merge-policy="PREFERRED_NON_NULL"/>
  <persistence passivation="false">
    <!-- Persistent storage configuration. -->
  </persistence>
</replicated-cache>
```

```
{
  "replicated-cache": {
    "mode": "SYNC",
    "segments": "256",
    "statistics": "true",
    "encoding": {
      "media-type": "application/x-protostream"
    },
    "locking": {
      "isolation": "REPEATABLE_READ"
    },
    "transaction": {
      "mode": "FULL_XA",
      "locking": "OPTIMISTIC"
    },
    "expiration" : {
      "lifespan" : "5000",
      "max-idle" : "1000"
    },
    "memory": {
      "max-count": "1000000",
      "when-full": "REMOVE"
    },
    "indexing" : {
      "enabled" : true,
      "storage" : "local-heap",
      "index-reader" : {
        "refresh-interval" : "1000"
      }
    },
    "partition-handling" : {
      "when-split" : "ALLOW_READ_WRITES",
      "merge-policy" : "PREFERRED_NON_NULL"
    },
    "persistence" : {
      "passivation" : false
    }
  }
}
```



```
replicatedCache:
  mode: "SYNC"
  segments: "256"
  statistics: "true"
  encoding:
    mediaType: "application/x-protostream"
  locking:
    isolation: "REPEATABLE_READ"
  transaction:
    mode: "FULL_XA"
    locking: "OPTIMISTIC"
  expiration:
    lifespan: "5000"
    maxIdle: "1000"
  memory:
    maxCount: "1000000"
    whenFull: "REMOVE"
  indexing:
    enabled: "true"
    storage: "local-heap"
    indexReader:
      refreshInterval: "1000"
  partitionHandling:
    whenSplit: "ALLOW_READ_WRITES"
    mergePolicy: "PREFERRED_NON_NULL"
  persistence:
    passivation: "false"
  # Persistent storage configuration.
```

## Multiple caches

```

<infinispan
  xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"
  xsi:schemaLocation="urn:infinispan:config:13.0
https://infinispan.org/schemas/infinispan-config-13.0.xsd
urn:infinispan:server:13.0
https://infinispan.org/schemas/infinispan-server-13.0.xsd"
  xmlns="urn:infinispan:config:13.0"
  xmlns:server="urn:infinispan:server:13.0">
  <cache-container name="default"
    statistics="true">
    <distributed-cache name="mycacheone"
      mode="ASYNC"
      statistics="true">
      <encoding media-type="application/x-protostream"/>
      <expiration lifespan="300000"/>
      <memory max-size="400MB"
        when-full="REMOVE"/>
    </distributed-cache>
    <distributed-cache name="mycachetwo"
      mode="SYNC"
      statistics="true">
      <encoding media-type="application/x-protostream"/>
      <expiration lifespan="300000"/>
      <memory max-size="400MB"
        when-full="REMOVE"/>
    </distributed-cache>
  </cache-container>
</infinispan>

```

```
infinispan:
  cacheContainer:
    name: "default"
    statistics: "true"
    caches:
      mycacheone:
        distributedCache:
          mode: "ASYNC"
          statistics: "true"
          encoding:
            mediaType: "application/x-protostream"
          expiration:
            lifespan: "300000"
          memory:
            maxSize: "400MB"
            whenFull: "REMOVE"
      mycachetwo:
        distributedCache:
          mode: "SYNC"
          statistics: "true"
          encoding:
            mediaType: "application/x-protostream"
          expiration:
            lifespan: "300000"
          memory:
            maxSize: "400MB"
            whenFull: "REMOVE"
```

```

{
  "infinispan" : {
    "cache-container" : {
      "name" : "default",
      "statistics" : "true",
      "caches" : {
        "mycacheone" : {
          "distributed-cache" : {
            "mode": "ASYNC",
            "statistics": "true",
            "encoding": {
              "media-type": "application/x-protostream"
            },
            "expiration" : {
              "lifespan" : "300000"
            },
            "memory": {
              "max-size": "400MB",
              "when-full": "REMOVE"
            }
          },
          "mycachetwo" : {
            "distributed-cache" : {
              "mode": "SYNC",
              "statistics": "true",
              "encoding": {
                "media-type": "application/x-protostream"
              },
              "expiration" : {
                "lifespan" : "300000"
              },
              "memory": {
                "max-size": "400MB",
                "when-full": "REMOVE"
              }
            }
          }
        }
      }
    }
  }
}

```

#### Additional resources

- [Infinispan configuration schema reference](#)
- [infinispan-config-13.0.xsd](#)

## 2.2. Modifying Infinispan cache configuration

Make changes to your remote cache configuration with the Infinispan CLI. You can modify attributes in your cache configuration either one at a time or provide a cache configuration in XML, JSON or YAML format to modify several attributes at once.

### Prerequisites

- Create at least one remote cache on your Infinispan cluster.

### Procedure

1. Create a CLI connection to Infinispan.
2. Modify the cache configuration with the **alter** command in one of the following ways:
  - Use the **--file** option to specify a configuration file with one or more attribute modifications.
  - Use the **--attribute** and **--value** option to modify a specific configuration attribute.



For more information and examples, run the **help alter** command.

3. Verify your changes with the **describe** command, for example:

```
describe caches/mycache
```

## 2.3. Adding Cache Entries

Create **key:value** pair entries in the data container.

### Prerequisites

Create a Infinispan cache that can store your data.

### Procedure

1. Create a CLI connection to Infinispan.
2. Add entries into your cache as follows:
  - Use the **--cache=** with the **put** command:

```
put --cache=mycache hello world
```

- Use the **put** command from the context of a cache:

```
[//containers/default/caches/mycache]> put hello world
```

3. Use the **get** command to verify entries.

```
[//containers/default/caches/mycache]> get hello  
world
```

## 2.4. Clearing Caches and Deleting Entries

Remove data from caches with the Infinispan CLI.

### *Procedure*

1. Create a CLI connection to Infinispan.
2. Do one of the following:
  - Delete all entries with the **clearcache** command.

```
clearcache mycache
```

- Remove specific entries with the **remove** command.

```
remove --cache=mycache hello
```

## 2.5. Deleting Caches

Drop caches to remove them and delete all data they contain.

### *Procedure*

1. Create a CLI connection to Infinispan.
2. Remove caches with the **drop** command.

```
drop cache mycache
```

## 2.6. Configuring Automatic Cache Rebalancing

By default, Infinispan automatically rebalances caches as nodes join and leave the cluster. You can configure automatic cache rebalancing by disabling or enabling it at the Cache Manager level or on a per-cache basis.

### *Procedure*

1. Create a CLI connection to Infinispan.
2. Disable automatic rebalancing for all caches with the **rebalance disable** command.

```
rebalance disable
```

3. Enable automatic rebalancing for a specific cache with the `rebalance enable` command.

The following example enables rebalancing for the cache named "mycache" only.

```
rebalance enable caches/mycache
```

4. Re-enable automatic rebalancing for all caches.

```
rebalance enable
```

For more information about the `rebalance` command, run `help rebalance`.

# Chapter 3. Performing Batch Operations

Process operations in groups, either interactively or using batch files.

## Prerequisites

- A running Infinispan cluster.

## 3.1. Performing Batch Operations with Files

Create files that contain a set of operations and then pass them to the Infinispan CLI.

### Procedure

1. Create a file that contains a set of operations.

For example, create a file named `batch` that creates a cache named `mybatch`, adds two entries to the cache, and disconnects from the CLI.

```
connect --username=<username> --password=<password> <hostname>:11222
create cache --template=org.infinispan.DIST_SYNC mybatch
put --cache=mybatch hello world
put --cache=mybatch hola mundo
ls caches/mybatch
disconnect
```



Configure the CLI with the `autoconnect-url` property instead of using the `connect` command directly in your batch files.

2. Run the CLI and specify the file as input.

```
bin/cli.sh -f batch
```



CLI batch files support system property expansion. Strings that use the `${property}` format are replaced with the value of the `property` system property.

## 3.2. Performing Batch Operations Interactively

Use the standard input stream, `stdin`, to perform batch operations interactively.

### Procedure

1. Start the Infinispan CLI in interactive mode.

```
bin/cli.sh -c localhost:11222 -f -
```





You can configure the CLI connection with the `autoconnect-url` property instead of using the `-c` argument.

## 2. Run batch operations, for example:

```
create cache --template=org.infinispan.DIST_SYNC mybatch
put --cache=mybatch hello world
put --cache=mybatch hola mundo
disconnect
quit
```



Use `echo` to add commands in interactive mode.

The following example shows how to use `echo describe` to get cluster information:

```
echo describe|bin/cli.sh -c localhost:11222 -f -
{
  "name" : "default",
  "version" : "10.0.0-SNAPSHOT",
  "coordinator" : false,
  "cache_configuration_names" : [ "org.infinispan.REPL_ASYNC", "___protobuf_metadata",
"org.infinispan.DIST_SYNC", "qcache", "org.infinispan.LOCAL", "dist_cache_01",
"org.infinispan.INVALIDATION_SYNC", "org.infinispan.REPL_SYNC",
"org.infinispan.SCATTERED_SYNC", "mycache", "org.infinispan.INVALIDATION_ASYNC",
"mybatch", "org.infinispan.DIST_ASYNC" ],
  "cluster_name" : "cluster",
  "physical_addresses" : "[192.168.1.7:7800]",
  "coordinator_address" : "thundercat-34689",
  "cache_manager_status" : "RUNNING",
  "created_cache_count" : "4",
  "running_cache_count" : "4",
  "node_address" : "thundercat-47082",
  "cluster_members" : [ "thundercat-34689", "thundercat-47082" ],
  "cluster_members_physical_addresses" : [ "10.36.118.25:7801", "192.168.1.7:7800" ],
  "cluster_size" : 2,
  "defined_caches" : [ {
    "name" : "___protobuf_metadata",
    "started" : true
  }, {
    "name" : "mybatch",
    "started" : true
  } ]
}
```

# Chapter 4. Configuring the Infinispan CLI

Define configuration properties for the Infinispan CLI.

## 4.1. Setting Infinispan CLI Properties and Persistent Storage

Configure Infinispan CLI startup operations and customize the location for persistent storage.

### Prerequisites

Create at least one Infinispan user.

### Procedure

1. Optionally set a custom path to the Infinispan CLI storage directory in one of the following ways:

- Using the `cli.dir` system property:

```
bin/cli.sh -Dcli.dir=/path/to/cli/storage ...
```

- Using the `ISPN_CLI_DIR` environment variable:

```
export ISPN_CLI_DIR=/path/to/cli/storage
bin/cli.sh ...
```

2. Set values for configuration properties with the `config set` command.

For example, set the `autoconnect-url` property so that the CLI automatically connects to that URL.



For remote connections, specify the URL and provide credentials:

- `http[s]://<username>:<password>@<hostname>:<port>` for basic authentication.
- `http[s]://<token>@<hostname>:<port>` for OAuth authentication.

```
bin/cli.sh config set autoconnect-url http://<username>:<password>@<hostname>:11222
```

3. Verify configuration properties with the `config get` command.



Run `help config` to review available configuration properties and get example usage.

## 4.2. Creating Command Aliases

Create aliases for Infinispan CLI commands to define custom shortcuts.

### Procedure

1. Create aliases with the `alias <alias>=<command>` command.

For example, set `q` as an alias for the `quit` command:

```
alias q=quit
```

2. Run the `alias` command to check the defined aliases.

```
alias
alias q='quit'
```

3. Delete aliases with the `unalias` command, for example:

```
unalias q
```

## 4.3. Trusting Infinispan Server Connections

Secure Infinispan CLI connections to Infinispan Server with SSL/TLS certificates. If you create a key store as an SSL identity for Infinispan Server, the CLI can validate server certificates to verify the identity.

### Prerequisites

- Set up an SSL identity for Infinispan Server.
- Create at least one Infinispan user.

### Procedure

1. Specify the location of the server key store, as in the following example:

```
bin/cli.sh config set truststore /home/user/my-trust-store.jks
```

2. Define the key store password, if necessary, as follows:

```
bin/cli.sh config set truststore-password secret
```

3. Verify your CLI configuration.

```
bin/cli.sh config get truststore
```

```
bin/cli.sh config get truststore-password
```

*Additional resources*

- [Setting Up SSL Identities for Infinispan Server](#)

## 4.4. Infinispan CLI Storage Directory

Infinispan CLI stores configuration in the following default directory:

Operating System	Default Path
Linux/Unix	<code>\$HOME/.config/{brandshortname}</code>
Microsoft Windows	<code>%APPDATA%/Sun/Java/{brandshortname}</code>
Mac OS	<code>\$HOME/Library/Java/{brandshortname}</code>

This directory contains the following files:

### **cli.properties**

Stores values for CLI configuration properties.

### **aliases**

Stores command aliases.

### **history**

Stores CLI history.

# Chapter 5. Working with Counters

Counters provide atomic increment and decrement operations that record the count of objects.

## Prerequisites

- Start the Infinispan CLI.
- Connect to a running Infinispan cluster.

## 5.1. Creating Counters

Create strong and weak counters with the Infinispan CLI.

### Procedure

1. Create a CLI connection to Infinispan.
2. Run the `create counter` command with the appropriate arguments.
  - a. Create `my-weak-counter`.

```
create counter --concurrency-level=1 --initial-value=5 --storage=PERSISTENT
--type=weak my-weak-counter
```

- b. Create `my-strong-counter`.

```
create counter --initial-value=3 --storage=PERSISTENT --type=strong my-strong-
counter
```

3. List available counters.

```
ls counters
```

4. Verify counter configurations.

- a. Describe `my-weak-counter`.

```
describe counters/my-weak-counter
```

```
{
  "weak-counter":{
    "initial-value":5,
    "storage":"PERSISTENT",
    "concurrency-level":1
  }
}
```

- b. Describe `my-strong-counter`.

```
describe counters/my-strong-counter
```

```
{
  "strong-counter":{
    "initial-value":3,
    "storage":"PERSISTENT",
    "upper-bound":5
  }
}
```

## 5.2. Adding Deltas to Counters

Increment or decrement counters with arbitrary values.

### Procedure

1. Select a counter.

```
counter my-weak-counter
```

2. List the current count.

```
[//containers/default/counters/my-weak-counter]> ls
5
```

3. Increment the counter value by `2`.

```
[//containers/default/counters/my-weak-counter]> add --delta=2
```

4. Decrement the counter value by `-4`.

```
[//containers/default/counters/my-weak-counter]> add --delta=-4
```



Strong counters return values after the operation is applied. Use `--quiet=true` to hide the return value.

For example, `add --delta=3 --quiet=true`.

Weak counters return empty responses.

# Chapter 6. Performing Cross-Site Replication Operations

Infinispan clusters running in different locations can discover and communicate with each other to backup data.

## Prerequisites

- Start the Infinispan CLI.
- Connect to a running Infinispan cluster.

## 6.1. Bringing backup locations offline and online

Take backup locations offline manually and bring them back online.

## Prerequisites

- Create a CLI connection to Infinispan.

## Procedure

1. Check if backup locations are online or offline with the `site status` command:

```
site status --cache=cacheName --site=NYC
```



`--site` is an optional argument. If not set, the CLI returns all backup locations.



Use the `--all-caches` option to get the backup location status for all caches.

2. Manage backup locations as follows:
  - Bring backup locations online with the `bring-online` command:

```
site bring-online --cache=customers --site=NYC
```

- Take backup locations offline with the `take-offline` command:

```
site take-offline --cache=customers --site=NYC
```



Use the `--all-caches` option to bring a backup location online, or take a backup location offline, for all caches.

For more information and examples, run the `help site` command.

## 6.2. Configuring cross-site state transfer modes

You can configure cross-site state transfer operations to happen automatically when Infinispan detects that backup locations come online. Alternatively you can use the default mode, which is to manually perform state transfer.

### Prerequisites

- Create a CLI connection to Infinispan.

### Procedure

1. Use the `site` command to configure state transfer modes, as in the following examples:
  - Retrieve the current state transfer mode.

```
site state-transfer-mode get --cache=cacheName --site=NYC
```

- Configure automatic state transfer operations for a cache and backup location.

```
site state-transfer-mode set --cache=cacheName --site=NYC --mode=AUTO
```



Run the `help site` command for more information and examples.

## 6.3. Pushing state to backup locations

Transfer cache state to backup locations.

### Prerequisites

- Create a CLI connection to Infinispan.

### Procedure

- Use the `site push-site-state` command to push state transfer, as in the following example:

```
site push-site-state --cache=cacheName --site=NYC
```



Use the `--all-caches` option to push state transfer for all caches.

For more information and examples, run the `help site` command.



# Chapter 7. Backing Up and Restoring Infinispan Clusters

Create archives of Infinispan resources that include cached entries, cache configurations, Protobuf schemas, and server scripts. You can then use the backup archives to restore Infinispan Server clusters after a restart or migration.

## *Prerequisites*

- Start the Infinispan CLI.
- Connect to a running Infinispan cluster.

## 7.1. Backing Up Infinispan Clusters

Create backup archives in **.zip** format that you can download or store on Infinispan Server.

## *Prerequisites*

Backup archives should reflect the most recent cluster state. For this reason you should ensure the cluster is no longer accepting write requests before you create backup archives.

## *Procedure*

1. Create a CLI connection to Infinispan.
2. Run the **backup create** command with the appropriate options, for example:
  - Back up all resources with an automatically generated name.

```
backup create
```

- Back up all resources in a backup archive named **example-backup**.

```
backup create -n example-backup
```

- Back up all resources to the **/some/server/dir** path on the server.

```
backup create -d /some/server/dir
```

- Back up only caches and cache templates.

```
backup create --caches=* --templates=*
```

- Back up named Protobuf schemas only.

```
backup create --proto-schemas=schema1,schema2
```

3. List available backup archives on the server.

```
backup ls
```

4. Download the **example-backup** archive from the server.

If the backup operation is still in progress, the command waits for it to complete.

```
backup get example-backup
```

5. Optionally delete the **example-backup** archive from the server.

```
backup delete example-backup
```

## 7.2. Restoring Infinispan Clusters from Backup Archives

Apply the content of backup archives to Infinispan clusters to restore them to the backed up state.

### *Prerequisites*

- Create a backup archive that is either local to the Infinispan CLI or stored on Infinispan Server.
- Ensure that the target container matches the container name in the backup archive. You cannot restore backups if the container names do not match.

### *Procedure*

1. Create a CLI connection to Infinispan.
2. Run the **backup restore** command with the appropriate options.
  - Restore all content from a backup archive accessible on the server.

```
backup restore /some/path/on/the/server
```

- Restore all content from a local backup archive.

```
backup restore -u /some/local/path
```

- Restore only cache content from a backup archive on the server.

```
backup restore /some/path/on/the/server --caches=*
```

# Chapter 8. Command Reference

Review manual pages for Infinispan CLI commands.



Use `help` command to access manual pages directly from your CLI session.

For example, to view the manual page for the `get` command do the following:

```
$ help get
```

## 8.1. ADD(1)

### 8.1.1. NAME

`add` - increments and decrements counters with arbitrary values.

### 8.1.2. SYNOPSIS

```
add ['OPTIONS'] ['COUNTER_NAME']
```

### 8.1.3. OPTIONS

`--delta='nnn'`

Sets a delta to increment or decrement the counter value. Defaults to `1`.

`-q, --quiet='[true|false]'`

Hides return values for strong counters. The default is `false`.

### 8.1.4. EXAMPLES

```
add --delta=10 cnt_a
```

Increments the value of `cnt_a` by `10`.

```
add --delta=-5 cnt_a
```

Decrements the value of `cnt_a` by `5`.

### 8.1.5. SEE ALSO

`cas(1)`, `reset(1)`

## 8.2. ALIAS(1)

### 8.2.1. NAME

`alias` - creates or displays aliases.

## 8.2.2. SYNOPSIS

**alias** ['ALIAS-NAME']='COMMAND']

## 8.2.3. EXAMPLES

**alias** q=quit

Creates **q** as an alias for the **quit** command.

**alias**

Lists all defined aliases.

## 8.2.4. SEE ALSO

config(1), unalias(1)

# 8.3. ALTER(1)

## 8.3.1. NAME

**alter** - modifies the configuration of caches on \${infinispan.brand.name} Server.

## 8.3.2. SYNOPSIS

**alter cache** ['OPTIONS'] **CACHE\_NAME**

You can modify a cache with the **alter** command only if the changes are compatible with the existing configuration.

For example you cannot use a replicated cache configuration to modify a distributed cache. Likewise if you create a cache configuration with a specific attribute, you cannot modify the configuration to use a different attribute instead. For example, attempting to modify cache configuration by specifying a value for the **max-count** attribute results in invalid configuration if the **max-size** is already set.

## 8.3.3. ALTER CACHE OPTIONS

**-f, --file='FILE'**

Specifies a configuration file in XML, JSON or YAML format that modifies an existing configuration. Mutually exclusive with the **--attribute** option.

**--attribute='ATTRIBUTE'**

Specifies an attribute to modify in an existing configuration. Press the tab key to display a list of attributes. Must be used in combination with the **--value** option. Mutually exclusive with the **--file** option.

**--value='VALUE'**

Specifies the new value for a configuration attribute. Must be used in combination with the

`--attribute` option.

### 8.3.4. EXAMPLES

```
alter cache mycache --file=/path/to/mycache.json
```

Modifies the configuration of a cache named `mycache` with the `mycache.json` file.

```
alter cache mycache --attribute=clustering.remote-timeout --value=5000
```

Modifies the configuration of a cache named `mycache` so that the `clustering.remote-timeout` attribute has a value of '5000'.

### 8.3.5. SEE ALSO

`create(1)`, `drop(1)`

## 8.4. AVAILABILITY(1)

### 8.4.1. NAME

`availability` - manage availability of clustered caches in network partitions.

### 8.4.2. SYNOPSIS

```
availability ['OPTIONS'] ['CACHE_NAME']
```

### 8.4.3. OPTIONS

```
--mode='[AVAILABLE|DEGRADED_MODE]'
```

Sets cache availability to `AVAILABLE` or `DEGRADED_MODE` when using either the `DENY_READ_WRITES` or `ALLOW_READS` partition handling strategy.

`AVAILABLE` makes caches available to all nodes in a network partition. `DEGRADED_MODE` prevents read and write operations on caches when network partitions occur.

### 8.4.4. EXAMPLES

```
availability cache1
```

Gets the current availability of the cache 'cache1'.

```
availability --mode=AVAILABLE cache1
```

Sets the availability of the cache 'cache1' to `AVAILABLE`.

## 8.5. BACKUP(1)

### 8.5.1. NAME

`backup` - manage container backup creation and restoration.

## 8.5.2. SYNOPSIS

**backup create** ['OPTIONS']

**backup delete** ['OPTIONS'] **BACKUP\_NAME**

**backup get** ['OPTIONS'] **BACKUP\_NAME**

**backup ls**

**backup restore** ['OPTIONS'] **BACKUP\_PATH**

## 8.5.3. BACKUP CREATE OPTIONS

**-d, --dir='PATH'**

Specifies a directory on the server to create and store the backup archive.

**-n, --name='NAME'**

Defines a name for the backup archive.

**--caches='cache1,cache2,...'**

Lists caches to back up. Use '\*' to back up all caches.

**--templates='template1,template2,...'**

Lists cache templates to back up. Use '\*' to back up all templates.

**--counters='counter1,counter2,...'**

Lists of counters to back up. Use '\*' to back up all counters.

**--proto-schemas='schema1,schema2,...'**

Lists Protobuf schemas to back up. Use '\*' to back up all schemas.

**--tasks='task1,task2,...'**

Lists server tasks to back up. Use '\*' to back up all tasks.

## 8.5.4. BACKUP GET OPTIONS

**--no-content**

Does not download content. The command returns only when the backup operation is complete.

## 8.5.5. BACKUP RESTORE OPTIONS

**-u, --upload**

Defines the path to a local backup archive that is uploaded to the server.

**-n, --name='NAME'**

Defines a name for the restore request.

**--caches='cache1,cache2,...'**

Lists caches to restore. Use '\*' to restore all caches from the backup archive.

**--templates='template1,template2,...'**

Lists cache templates to restore. Use '\*' to restore all templates from the backup archive.

**--counters='counter1,counter2,...'**

Lists counters to restore. Use '\*' to restore all counters from the backup archive.

**--proto-schemas='schema1,schema2,...'**

Lists Protobuf schemas to restore. Use '\*' to restore all schemas from the backup archive.

**--tasks='task1,task2,...'**

Lists server tasks to restore. Use '\*' to restore all tasks from the backup archive.

## 8.5.6. EXAMPLES

`backup create -n example-backup`

Initiates a backup of all container content with name `example-backup`.

`backup create -d /some/server/dir`

Initiates a backup of all container content and stores it on the server at path `/some/server/dir`.

`backup create --caches=* --templates=*`

Initiates a backup that contains only cache and cache configuration resources.

`backup create --proto-schemas=schema1,schema2`

Initiates a backup that contains the named schema resources only.

`backup ls`

Lists all backups available on the server.

`backup get example-backup`

Downloads the `example-backup` archive from the server. If the backup operation is in progress, the command waits for it to complete.

`backup restore /some/path/on/the/server`

Restores all content from a backup archive on the server.

`backup restore -u /some/local/path`

Restores all content from a local backup archive that is uploaded to the server.

`backup restore /some/path/on/the/server --caches=*`

Restores only cache content from a backup archive on the server.

`backup restore /some/path/on/the/server --proto-schemas=schema1,schema2`

Restores only the named schema resources from a backup archive on the server.

`backup delete example-backup`

Deletes the `example-backup` archive from the server.



## 8.5.7. SEE ALSO

drop(1)

## 8.6. BENCHMARK(1)

### 8.6.1. NAME

benchmark - runs a performance benchmark against a cache.

You can run performance benchmarks for the following HTTP and Hot Rod protocols: [http](#), [https](#), [hotrod](#), and [hotrods](#). You specify the protocol for the benchmark with a URI. If you do not specify a protocol, the benchmark uses the URI of the current CLI connection.

Benchmarks for Hot Rod URIs connect to the entire cluster. For HTTP URIs, benchmarks connect to a single node only.

Benchmarks test performance against an existing cache. Before you run a benchmark, you should create a cache with the capabilities you want to measure. For example, if you want to evaluate the performance of cross-site replication, you should create a cache that has backup locations. If you want to test the performance of persistence, create a cache that uses an appropriate cache store.

### 8.6.2. SYNOPSIS

**benchmark** ['OPTIONS'] [[uri](#)]

### 8.6.3. BENCHMARK OPTIONS

**-t, --threads='num'**

Specifies the number of threads to create. Defaults to [10](#).

**--cache='cache'**

Names the cache against which the benchmark is performed. Defaults to [benchmark](#). You must create the cache before running the benchmark if it does not already exist.

**\*--key-size='num'**

Sets the size, in bytes, of the key. Defaults to 16 bytes.

**\*--value-size='num'**

Sets the size, in bytes, of the value. Defaults to 1000 bytes.

**\*--keyset-size='num'**

Defines the size, in bytes, of the test key set. Defaults to [1000](#).

**--verbosity=['SILENT', 'NORMAL', 'EXTRA']**

Specifies the verbosity level of the output. Possible values, from least to most verbose, are [SILENT](#), [NORMAL](#), and [EXTRA](#). The default is [NORMAL](#).

**-c, --count='num'**

Specifies how many measurement iterations to perform. Defaults to 5.

**--time='time'**

Sets the amount of time, in seconds, that each iteration takes. Defaults to 10.

**--warmup-count='num'**

Specifies how many warmup iterations to perform. Defaults to 5.

**--warmup-time='time'**

Sets the amount of time, in seconds, that each warmup iteration takes. Defaults to 1.

**--mode='mode'**

Specifies the benchmark mode. Possible values are `Throughput`, `AverageTime`, `SampleTime`, `SingleShotTime`, and `All`. The default is `Throughput`.

**--time-unit='unit'**

Specifies the time unit for results in the benchmark report. Possible values are `NANOSECONDS`, `MICROSECONDS`, `MILLISECONDS`, and `SECONDS`. The default is `MICROSECONDS`.

## 8.6.4. EXAMPLES

```
benchmark hotrod://localhost:11222
```

Performs a benchmark test with the Hot Rod protocol.

```
benchmark --value-size=10000 --cache=largecache hotrod://localhost:11222
```

Performs a benchmark test with the Hot Rod protocol against the `largecache` cache using test values that are 10000 bytes in size.

```
benchmark --mode=All --threads=20 https://user:password@server:11222
```

Performs a benchmark test with the HTTPS protocol using 20 threads and includes all modes in the report.

## 8.7. CACHE(1)

### 8.7.1. NAME

`cache` - selects the default cache for subsequent commands.

### 8.7.2. SYNOPSIS

```
cache ['CACHE_NAME']
```

### 8.7.3. EXAMPLE

```
cache mycache
```

Selects `mycache` and is the same as navigating the resource tree using `cd caches/mycache`.

#### 8.7.4. SEE ALSO

cd(1), clear(1), container(1), get(1), put(1), remove(1)

## 8.8. CAS(1)

### 8.8.1. NAME

cas - performs 'compare-and-swap' operations on strong counters.

### 8.8.2. SYNOPSIS

**cas** ['OPTIONS'] ['COUNTER\_NAME']

### 8.8.3. OPTIONS

**--expect='nnn'**

Specifies the expected value of the counter.

**--value='nnn'**

Sets a new value for the counter.

**-q, --quiet='[true|false]'**

Hides return values. The default is false.

### 8.8.4. EXAMPLE

```
cas --expect=10 --value=20 cnt_a
```

Sets the value of `cnt_a` to 20 only if the current value is 10

### 8.8.5. SEE ALSO

add(1), cas(1), reset(1)

## 8.9. CD(1)

### 8.9.1. NAME

cd - navigates the server resource tree.

### 8.9.2. DESCRIPTION

`PATH` can be absolute or relative to the current resource. `../` specifies parent resources.

### 8.9.3. SYNOPSIS

**cd** ['PATH']

## 8.9.4. EXAMPLE

`cd caches`

Changes to the `caches` path in the resource tree.

## 8.9.5. SEE ALSO

`cache(1)`, `ls(1)`, `container(1)`

# 8.10. CLEARCACHE(1)

## 8.10.1. NAME

`clearcache` - removes all entries from a cache.

## 8.10.2. SYNOPSIS

`clearcache` ['CACHE\_NAME']

## 8.10.3. EXAMPLES

`clearcache mycache`

Removes all entries from `mycache`.

## 8.10.4. SEE ALSO

`cache(1)`, `drop(1)`, `remove(1)`

# 8.11. CONFIG(1)

## 8.11.1. NAME

`config` - manages CLI configuration properties.

## 8.11.2. SYNOPSIS

`config`

`config set` 'name' 'value'

`config get` 'name'

`config convert` --outputFormat=[xml|json|yaml] [-o outputFile] [inputFile]

## 8.11.3. DESCRIPTION

Manage (list, set, get) CLI configuration properties and provide configuration conversion between the different formats (XML, JSON, YAML)

## 8.11.4. COMMAND SYNOPSIS

### **config**

Lists all configuration properties that are set.

### **config set 'name' ['value']**

Sets the value of a specific property. If you do not specify a value, the property is not set.

### **config get 'name'**

Retrieves the value of a specific property.

### **config convert --format=[xml|json|yaml] [-o outputFile] [inputFile]**

Converts a configuration file to a different format.

## 8.11.5. COMMON OPTIONS

These options apply to all commands:

### **-h, --help**

Displays a help page for the command or sub-command.

## 8.11.6. CONVERT OPTIONS

The following options apply to the **convert** command:

### **-f, --format='xml|json|yaml'**

Specifies the format for the conversion.

### **-o, --output='path'**

Specifies the path to the output file. Uses standard output (**stdout**) if you do not specify a path.

## 8.11.7. PROPERTIES

### **autoconnect-url**

Specifies the URL to which the CLI automatically connects on startup.

### **autoexec**

Specifies the path of a CLI batch file to execute on startup.

### **trustall**

Specifies whether to trust all server certificates. Values are **false** (default) and **true**.

### **truststore**

Defines the path to a keystore that contains a certificate chain that verifies server identity.

### **truststore-password**

Specifies a password to access the keystore.

## 8.11.8. EXAMPLES

```
config set autoconnect-url http://192.0.2.0:11222
```

Connects to a server at a custom IP address when you start the CLI.

```
config get autoconnect-url
```

Returns the value for the `autoconnect-url` configuration property.

```
config set autoexec /path/to/mybatchfile
```

Runs a batch file named "mybatchfile" when you start the CLI.

```
config set trustall true
```

Trusts all server certificates.

```
config set truststore /home/user/my-trust-store.jks
```

Specifies the path of a keystore named "my-trust-store.jks".

```
config set truststore-password secret
```

Sets the keystore password, if required.

```
config convert -f yaml -o infinispn.yaml infinispn.xml
```

Converts the `infinispn.xml` file to YAML and writes the output to the `infinispn.yaml` file.

```
config convert -f json
```

Converts the configuration from standard input to JSON, and writes the output to standard output.

## 8.11.9. SEE ALSO

`alias(1)`, `unalias(1)`

## 8.12. CONNECT(1)

### 8.12.1. NAME

`connect` - connects to running `${infinispn.brand.name}` servers.

### 8.12.2. DESCRIPTION

Defaults to `http://localhost:11222` and prompts for credentials if authentication is required.

### 8.12.3. SYNOPSIS

```
connect ['OPTIONS'] ['SERVER_LOCATION']
```

### 8.12.4. OPTIONS

**-u, --username='USERNAME'**

Specifies a username to authenticate with `${infinispn.brand.name}` servers.

**-p, --password='PASSWORD'**

Specifies passwords.

### 8.12.5. EXAMPLE

```
connect 127.0.0.1:11322 -u test -p changeme
```

Connects to a locally running server using a port offset of **100** and example credentials.

### 8.12.6. SEE ALSO

disconnect(1)

## 8.13. CONTAINER(1)

### 8.13.1. NAME

container - selects the container for running subsequent commands.

### 8.13.2. SYNOPSIS

**container** ['CONTAINER\_NAME']

### 8.13.3. EXAMPLE

```
container default
```

Selects the default container and is the same as navigating the resource tree using **cd containers/default**.

### 8.13.4. SEE ALSO

cd(1), clear(1), container(1), get(1), put(1), remove(1)

## 8.14. COUNTER(1)

### 8.14.1. NAME

counter - selects the default counter for subsequent commands.

### 8.14.2. SYNOPSIS

**counter** ['COUNTER\_NAME']

### 8.14.3. EXAMPLE

```
counter cnt_a
```

Selects **cnt\_a** and is the same as navigating the resource tree using **cd counters/cnt\_a**.

#### 8.14.4. SEE ALSO

add(1), cas(1)

### 8.15. CREATE(1)

#### 8.15.1. NAME

create - creates caches and counters on \${infinispan.brand.name} servers.

#### 8.15.2. SYNOPSIS

**create cache** ['OPTIONS'] **CACHE\_NAME**

**create counter** ['OPTIONS'] **COUNTER\_NAME**

#### 8.15.3. CREATE CACHE OPTIONS

**-f, --file='FILE'**

Specifies a configuration file in XML, JSON or YAML format.

**-t, --template='TEMPLATE'**

Specifies a configuration template. Use tab autocompletion to see available templates.

**-v, --volatile='[true | false]'**

Specifies whether the cache is persistent or volatile. The default is false.

#### 8.15.4. CREATE COUNTER OPTIONS

**-t, --type='[weak | strong]'**

Specifies if the counter is weak or strong.

**-s, --storage='[PERSISTENT | VOLATILE]'**

Specifies whether the counter is persistent or volatile.

**-c, --concurrency-level='nnn'**

Sets the concurrency level of the counter.

**-i, --initial-value='nnn'**

Sets the initial value of the counter.

**-l, --lower-bound='nnn'**

Sets the lower bound of a **strong** counter.

**-u, --upper-bound='nnn'**

Sets the upper bound of a **strong** counter.



### 8.15.5. EXAMPLES

```
create cache --template=org.infinispan.DIST_SYNC mycache
```

Creates a cache named `mycache` from the `DIST_SYNC` template.

```
create counter --initial-value=3 --storage=PERSISTENT --type=strong cnt_a
```

Creates a strong counter named `cnt_a`.

### 8.15.6. SEE ALSO

`drop(1)`

## 8.16. CREDENTIALS(1)

### 8.16.1. NAME

`credentials` - manages keystores that contain `${infinispan.brand.name}` Server credentials

### 8.16.2. SYNOPSIS

**`credentials ls`**

**`credentials add 'alias'`**

**`credentials remove 'alias'`**

### 8.16.3. DESCRIPTION

List, create, and remove credentials inside a keystore. By default, commands manage the `credentials.pfx` keystore in the server configuration directory.

### 8.16.4. SYNOPSIS

**`credentials ls`**

Lists credential aliases stored in the keystore.

Add a credential

**`credentials add 'alias'`**

Adds an alias and corresponding credential to the keystore.

Remove a credential

**`credentials remove 'alias'`**

Deletes an alias and corresponding credential from the keystore.

### 8.16.5. OPTIONS

**`-h, --help`**

Prints command help.

**-s, --server-root='path-to-server-root'**

Specifies the path to the server root directory. Defaults to `server`.

**--path='credentials.pfx'**

Specifies the path to the credential keystore. Defaults to the server configuration directory, `server/conf`.

**-p, --password='password'**

Specifies a password for the credential keystore.

**-t, --type='PKCS12'**

Specifies the type of keystore that contains credentials. Supported types are `PKCS12` or `JCEKS`. Defaults to `PKCS12`.

## 8.16.6. CREDENTIALS ADD OPTIONS

**-c, --credential='credential'**

Specifies the credential to store.

## 8.16.7. EXAMPLES

```
credentials add dbpassword -c changeme -p "secret1234!"
```

Creates a new default credential keystore, if does not already exist, and adds an alias of "dbpassword" for a password of "changeme". This command also sets "secret1234!" as the password for the credential keystore, which must match the password in the server configuration: `<clear-text-credential clear-text="secret1234!"/>`

```
credentials ls -p "secret1234!"
```

Lists all aliases in the default credential keystore.

```
credentials add ldappassword -t JCEKS -p "secret1234!"
```

Creates a credential keystore in JCEKS format and adds an alias "ldappassword". This command prompts you to specify the password that corresponds to the alias.

## 8.17. DESCRIBE(1)

### 8.17.1. NAME

describe - displays information about resources.

### 8.17.2. SYNOPSIS

**describe** [**PATH**]

### 8.17.3. EXAMPLES

`describe //containers/default`

Displays information about the default container.

`describe //containers/default/caches/mycache`

Displays information about the `mycache` cache.

`describe //containers/default/caches/mycache/k1`

Displays information about the `k1` key.

`describe //containers/default/counters/cnt1`

Displays information about the `cnt1` counter.

### 8.17.4. SEE ALSO

`cd(1)`, `ls(1)`

## 8.18. DISCONNECT(1)

### 8.18.1. NAME

`disconnect` - ends CLI sessions with `${infinispan.brand.name}` servers.

### 8.18.2. SYNOPSIS

`disconnect`

### 8.18.3. EXAMPLE

`disconnect`

Ends the current CLI session.

### 8.18.4. SEE ALSO

`connect(1)`

## 8.19. DROP(1)

### 8.19.1. NAME

`drop` - deletes caches and counters.

### 8.19.2. SYNOPSIS

`drop cache` `CACHE_NAME`

`drop counter` `COUNTER_NAME`

### 8.19.3. EXAMPLES

`drop cache mycache`

Deletes the `mycache` cache.

`drop counter cnt_a`

Deletes the `cnt_a` counter.

### 8.19.4. SEE ALSO

`create(1)`, `clearcache(1)`

## 8.20. ENCODING(1)

### 8.20.1. NAME

`encoding` - displays and sets the encoding for cache entries.

### 8.20.2. DESCRIPTION

Sets a default encoding for **put** and **get** operations on a cache. If no argument is specified, the **encoding** command displays the current encoding.

Valid encodings use standard MIME type (IANA media types) naming conventions, such as the following:

- `text/plain`
- `application/json`
- `application/xml`
- `application/octet-stream`

### 8.20.3. SYNOPSIS

**encoding** ['ENCODING']

### 8.20.4. EXAMPLE

`encoding application/json`

Configures the currently selected cache to encode entries as `application/json`.

### 8.20.5. SEE ALSO

`get(1)`, `put(1)`

## 8.21. GET(1)

### 8.21.1. NAME

get - retrieves entries from a cache.

### 8.21.2. SYNOPSIS

**get** ['OPTIONS'] **KEY**

### 8.21.3. OPTIONS

**-c, --cache='NAME'**

Specifies the cache from which to retrieve entries. Defaults to the currently selected cache.

### 8.21.4. EXAMPLE

**get** **hello** -c **mycache**

Retrieves the value of the key named **hello** from **mycache**.

### 8.21.5. SEE ALSO

query(1), put(1)

## 8.22. HELP(1)

### 8.22.1. NAME

help - prints manual pages for commands.

### 8.22.2. SYNOPSIS

**help** ['COMMAND']

### 8.22.3. EXAMPLE

**help** **get**

Prints the manual page for the **get** command.

### 8.22.4. SEE ALSO

version(1)

## 8.23. INSTALL(1)

### 8.23.1. NAME

install - download and install artifacts for \${infinispan.brand.name} Server.

### 8.23.2. DESCRIPTION

Download and install artifacts to the `server/lib` directory. You can specify the download location for artifacts as Maven artifact coordinates, a URL, or a local file path.

When downloading Maven artifacts, an optional Maven `settings.xml` file determines the location of the remote and local repositories as well as credentials and proxy configuration.

If you download artifacts as `zip`, `tar.gz`, or `tgz` archives, the content is extracted.

### 8.23.3. SYNOPSIS

```
install 'artifact-1[| algorithm| checksum]' ['artifact-2[| algorithm| checksum]'...]
```

### 8.23.4. ARTIFACT NAMES

Artifact names can be any of the following:

- Maven coordinates using the `groupId:artifactId:version` format, for example `org.postgresql:postgresql:42.3.1`.
- HTTP, HTTPS, or FTP URLs
- Local paths

### 8.23.5. CHECKSUM VALIDATION

You can validate the checksum of an artifact after download. The algorithm defaults to `SHA-256` but it can also be `MD-5`, `SHA-1`, `SHA-256`, `SHA-384`, or `'SHA-512'`.

### 8.23.6. PATCH LIST OPTIONS

**--server-home='path/to/server'**

Sets the path of the server installation.

**--server-root='server'**

Sets the server root directory relative to the server home.

**\*--maven-settings='\$HOME/.m2/maven-settings.xml'**

Sets the path of a Maven `settings.xml` file and uses the default location, if not specified.

**-o, --overwrite**

Forces overwriting of artifacts in the `server/lib` directory. By default artifacts are not overwritten, which causes the installation to fail if an artifact already exists.

**-v, --verbose**

Shows verbose information about artifact downloads.

**-f, --force**

Forces download of remote artifacts, even if they are already present locally.

**-r, --retries=num**

The number of retries in case the downloaded artifacts do not match the supplied checksums.

**--clean**

Deletes all the contents of the **server/lib** directory before downloading artifacts.

## 8.23.7. EXAMPLES

**install -o org.postgresql:postgresql:42.3.1**

Installs the PostgreSQL JDBC driver JAR and overwrites if it already exists.

**install <https://example.org/artifact.zip>**

Downloads the **artifact.zip** and extracts the contents.

**install <https://example.org/artifact.zip|52d73f9b3611610ebbb4dca7c2ac1171218eb09891c1faba10f5f54c1d2acc13>**

Downloads the **artifact.zip**, verifies its SHA-256 checksum, and extracts the contents.

**install <https://example.org/artifact.zip|MD5|2b48d1871ee26f969d8481db94e103c2>**

Downloads the **artifact.zip**, verifies its MD-5 checksum, and extracts the contents.

## 8.24. LOGGING(1)

### 8.24.1. NAME

logging - inspects and manipulates the `${infinispan.brand.name}` server runtime logging configuration.

### 8.24.2. SYNOPSIS

**logging list-loggers**

**logging list-appenders**

**logging set** ['OPTIONS'] [**LOGGER\_NAME**]

**logging remove** **LOGGER\_NAME**

### 8.24.3. LOGGING SET OPTIONS

**-l, --level='OFF|TRACE|DEBUG|INFO|WARN|ERROR|ALL'**

Specifies the logging level for the specific logger.

**-a, --appender='APPENDER'**

Specifies an appenders to set on the specific logger. The option can be repeated for multiple appenders.



calling **logging set** without a logger name will modify the root logger.

## 8.24.4. EXAMPLES

`logging list-loggers`

Lists all available loggers

`logging set --level=DEBUG --appenders=FILE org.infinispan`

Sets the log level for the `org.infinispan` logger to `DEBUG` and configures it to use the `FILE` appender.

## 8.25. LS(1)

### 8.25.1. NAME

`ls` - lists resources for the current path or a given path.

### 8.25.2. SYNOPSIS

`ls ['PATH']`

### 8.25.3. EXAMPLES

`ls caches`

Lists the available caches.

`ls ../`

Lists parent resources.

### 8.25.4. SEE ALSO

`cd(1)`

## 8.26. MIGRATE(1)

### 8.26.1. NAME

`migrate` - migrates data from one version of `${infinispan.brand.name}` to another.

### 8.26.2. SYNOPSIS

`migrate cluster connect`

`migrate cluster synchronize`

`migrate cluster disconnect`

`migrate cluster source-connection`

### 8.26.3. DESCRIPTION

Use the `migrate` command to migrate data from one version of `${infinispan.brand.name}` to



another.

## 8.26.4. COMMAND SYNOPSIS

Migrate clusters

### **migrate cluster connect**

Connects the target cluster to the source cluster.

### **migrate cluster synchronize**

Synchronize data between the source cluster and the target cluster.

### **migrate cluster disconnect**

Disconnects the target cluster from the source cluster.

### **migrate cluster source-connection**

Gets connection configuration of the target cluster. The command will print "Not Found" if the connections hasn't been established.

## 8.26.5. COMMON OPTIONS

These options apply to all commands:

### **-h, --help**

Displays a help page for the command or sub-command.

### CLUSTER CONNECT OPTIONS

**\*-c, --cache\*='name'::**

The name of the cache to connect to the source.

**\*-f, --file\*='FILE'::**

Specifies a configuration file in JSON format, containing a single 'remote-store' element.

### CLUSTER SYNCHRONIZE OPTIONS

-----

**\*-c, --cache\*='name'::**

The name of the cache to synchronize.

**\*-b, --read-batch\*='num'::**

The amount of entries to process in a batch. Defaults to 10000.

**\*-t, --threads\*='num'::**

The number of threads to use. Defaults to the number of cores on the server.

### CLUSTER DISCONNECT OPTIONS

**-c, --cache='name'**

The name of the cache to disconnect from the source.

## 8.26.6. CLUSTER CONNECTION OPTIONS

**-c, --cache='name'**

The name of the cache to obtain the connection configuration.

## 8.27. PATCH(1)

### 8.27.1. NAME

patch - manages server patches.

### 8.27.2. DESCRIPTION

List, describe, install, rollback, and create server patches.

Patches are zip archive files that contain artifacts to upgrade servers and resolve issues or add new features. Patches can apply target versions to multiple server installations with different versions.

### 8.27.3. SYNOPSIS

**patch ls**

**patch install** 'patch-file'

**patch describe** 'patch-file'

**patch rollback**

**patch create** 'patch-file' 'target-server' 'source-server-1' ['source-server-2'...]

### 8.27.4. PATCH LIST OPTIONS

**--server='path/to/server'**

Sets the path to a target server outside the current server home directory.

**-v, --verbose**

Shows the content of each installed patch, including information about individual files.

### 8.27.5. PATCH INSTALL OPTIONS

**--dry-run**

Shows the operations that the patch performs without applying any changes.

**--server='path/to/server'**

Sets the path to a target server outside the current server home directory.

## 8.27.6. PATCH DESCRIBE OPTIONS

### **-v, --verbose**

Shows the content of the patch, including information about individual files

## 8.27.7. PATCH ROLLBACK OPTIONS

### **--dry-run**

Shows the operations that the patch performs without applying any changes.

### **--server='path/to/server'**

Sets the path to a target server outside the current server home directory.

## 8.27.8. PATCH CREATE OPTIONS

### **-q, --qualifier='name'**

Specifies a descriptive qualifier string for the patch; for example, 'one-off for issue nnnn'.

## 8.27.9. EXAMPLES

```
patch ls
```

Lists the patches currently installed on a server in order of installation.

```
patch install mypatch.zip
```

Installs "mypatch.zip" on a server in the current directory.

```
patch install mypatch.zip --server=/path/to/server/home
```

Installs "mypatch.zip" on a server in a different directory.

```
patch describe mypatch.zip
```

Displays the target version and list of source versions for "mypatch.zip".

```
patch create mypatch.zip 'target-server' 'source-server-1' ['source-server-2'...]
```

Creates a patch file named "mypatch.zip" that uses the version of the target server and applies to the source server versions.

```
patch rollback
```

Rolls back the last patch that was applied to a server and restores the previous version.

## 8.28. PUT(1)

### 8.28.1. NAME

put - adds or updates cache entries.

### 8.28.2. DESCRIPTION

Creates entries for new keys. Replaces values for existing keys.

### 8.28.3. SYNOPSIS

**put** ['OPTIONS'] **KEY** [VALUE]

### 8.28.4. OPTIONS

**-c, --cache='NAME'**

Specifies the name of the cache. Defaults to the currently selected cache.

**-e, --encoding='ENCODING'**

Sets the media type for the value.

**-f, --file='FILE'**

Specifies a file that contains the value for the entry.

**-l, --ttl='TTL'**

Sets the number of seconds before the entry is automatically deleted (time-to-live). Defaults to the value for **lifespan** in the cache configuration if **0** or not specified. If you set a negative value, the entry is never deleted.

**-i, --max-idle='MAXIDLE'**

Sets the number of seconds that the entry can be idle. If a read or write operation does not occur for an entry after the maximum idle time elapses, the entry is automatically deleted. Defaults to the value for **maxIdle** in the cache configuration if **0** or not specified. If you set a negative value, the entry is never deleted.

**-a, --if-absent=[true | false]**

Puts an entry only if it does not exist.

### 8.28.5. EXAMPLES

```
put -c mycache hello world
```

Adds the **hello** key with a value of **world** to the **mycache** cache.

```
put -c mycache -f myfile -i 500 hola
```

Adds the **hola** key with the value from the contents of **myfile**. Also sets a maximum idle of **500** seconds.

### 8.28.6. SEE ALSO

`get(1)`, `remove(1)`

## 8.29. QUERY(1)

### 8.29.1. NAME

**query** - performs Ickle queries to match entries in remote caches.

## 8.29.2. SYNOPSIS

**query** ['OPTIONS'] **QUERY\_STRING**

## 8.29.3. OPTIONS

**-c, --cache='NAME'**

Specifies the cache to query. Defaults to the currently selected cache.

**--max-results='MAX\_RESULTS'**

Sets the maximum number of results to return. The default is **10**.

**-o, --offset='OFFSET'**

Specifies the index of the first result to return. The default is **0**.

## 8.29.4. EXAMPLES

```
query "from org.infinispan.example.Person p where p.gender = 'MALE'"
```

Queries values in a remote cache to find entries from a Protobuf **Person** entity where the gender datatype is **MALE**.

## 8.29.5. SEE ALSO

schema(1)

# 8.30. QUIT(1)

## 8.30.1. NAME

quit - exits the command line interface.

## 8.30.2. SYNOPSIS

**quit**

**exit** and **bye** are command aliases.

## 8.30.3. EXAMPLE

**quit**

Ends the CLI session.

**exit**

Ends the CLI session.

**bye**

Ends the CLI session.

#### 8.30.4. SEE ALSO

disconnect(1), shutdown(1)

## 8.31. REBALANCE(1)

### 8.31.1. NAME

rebalance - manages automatic rebalancing for caches

### 8.31.2. SYNOPSIS

**rebalance enable** ['PATH']

**rebalance disable** ['PATH']

### 8.31.3. EXAMPLES

**rebalance enable**

Enables automatic rebalancing in the current context. Running this command in the root context enables rebalancing for all caches.

**rebalance enable caches/mycache**

Enables automatic rebalancing for the cache named **mycache**.

**rebalance disable**

Disables automatic rebalancing in the current context. Running this command in the root context disables rebalancing for all caches.

**rebalance disable caches/mycache**

Disables automatic rebalancing for the cache named **mycache**.

## 8.32. REMOVE(1)

### 8.32.1. NAME

remove - deletes entries from a cache.

### 8.32.2. SYNOPSIS

**remove** **KEY** ['OPTIONS']

### 8.32.3. OPTIONS

**--cache='NAME'**

Specifies the cache from which to remove entries. Defaults to the currently selected cache.

#### 8.32.4. EXAMPLE

```
remove --cache=mycache hola
```

Deletes the `hola` entry from the `mycache` cache.

#### 8.32.5. SEE ALSO

cache(1), drop(1), clearcache(1)

### 8.33. RESET(1)

#### 8.33.1. NAME

reset - restores the initial values of counters.

#### 8.33.2. SYNOPSIS

```
reset ['COUNTER_NAME']
```

#### 8.33.3. EXAMPLE

```
reset cnt_a
```

Resets the `cnt_a` counter.

#### 8.33.4. SEE ALSO

add(1), cas(1), drop(1)

### 8.34. SCHEMA(1)

#### 8.34.1. NAME

schema - uploads and registers protobuf schemas.

#### 8.34.2. SYNOPSIS

```
schema ['OPTIONS'] SCHEMA_NAME
```

#### 8.34.3. OPTIONS

```
-u, --upload='FILE'
```

Uploads a file as a protobuf schema with the given name.

#### 8.34.4. EXAMPLE

```
schema --upload=person.proto person.proto
```

Registers a `person.proto` Protobuf schema.

### 8.34.5. SEE ALSO

query(1)

## 8.35. SERVER(1)

### 8.35.1. NAME

server - server configuration and state management.

### 8.35.2. DESCRIPTION

The **server** command describes and manages server endpoint connectors and datasources and retrieves aggregated diagnostic reports about both the server and host.

Reports provide details about CPU, memory, open files, network sockets and routing, threads, in addition to configuration and log files.

### 8.35.3. SYNOPSIS

**server report**

**server connector ls**

**server connector describe** 'connector-name'

**server connector start** 'connector-name'

**server connector stop** 'connector-name'

**server connector ipfilter ls** 'connector-name'

**server connector ipfilter set** 'connector-name' --rules='[ACCEPT|REJECT]/cidr',...

**server connector ipfilter clear** 'connector-name'

**server datasource ls**

**server datasource test** 'datasource-name'

### 8.35.4. SERVER CONNECTOR IPFILTER OPTIONS

**--rules='[ACCEPT|REJECT]/cidr',...**

One or more IP filtering rules.

### 8.35.5. EXAMPLES

**server report**

Obtains a server report, including information about network, threads, memory, etc.



`server connector ls`

Lists all available connectors on the server.

`server connector describe endpoint-default`

Shows information about the specified connector, including host, port, local and global connections, IP filtering rules.

`server connector stop my-hotrod-connector`

Stops a connector dropping all established connections across the cluster. This command will be refused if attempting to stop the connector which is handling the request.

`server connector start my-hotrod-connector`

Starts a connector so that it can accept connections across the cluster.

`server connector ipfilter ls my-hotrod-connector`

Lists all IP filtering rules active on a connector across the cluster.

`server connector ipfilter set my-hotrod-connector --rules=ACCEPT/192.168.0.0/16,REJECT/10.0.0.0/8` Sets IP filtering rules on a connector across the cluster. Replaces all existing rules. This command will be refused if one of the rejection rules matches the address of the connection on which it is invoked.

`server connector ipfilter clear my-hotrod-connector`

Removes all IP filtering rules on a connector across the cluster.

`server datasource ls`

Lists all available datasources on the server.

`server datasource test my-datasource`

Performs a test connection on the datasource.

## 8.36. SHUTDOWN(1)

### 8.36.1. NAME

shutdown - stops server instances and clusters.

### 8.36.2. SYNOPSIS

**shutdown server** ['SERVERS']

**shutdown cluster**

**shutdown container**

### 8.36.3. EXAMPLES

`shutdown server`

Stops the server to which the CLI is connected.

**shutdown server my\_server01**

Stops the server with hostname **my\_server01**.

**shutdown cluster**

Stops all nodes in the cluster after storing cluster state and persisting entries if there is a cache store.

**shutdown container**

Stops the data container without terminating the server process. Stores cluster state and persists entries if there is a cache store. Server instances remain running with active endpoints and clustering. REST calls to container resources will result in a 503 Service Unavailable response. The **shutdown container** command is intended for environments, such as Kubernetes, that automate resource lifecycle management. For self-managed environments you should use the **shutdown server** or **shutdown cluster** commands to stop servers.

## 8.36.4. SEE ALSO

**connect(1)**, **disconnect(1)**, **quit(1)**

## 8.37. SITE(1)

### 8.37.1. NAME

**site** - manages backup locations and performs cross-site replication operations.

### 8.37.2. SYNOPSIS

**site status** ['OPTIONS']

**site bring-online** ['OPTIONS']

**site take-offline** ['OPTIONS']

**site push-site-state** ['OPTIONS']

**site cancel-push-state** ['OPTIONS']

**site cancel-receive-state** ['OPTIONS']

**site push-site-status** ['OPTIONS']

**site state-transfer-mode** **get** | **set** ['OPTIONS']

**site name**

**site view**

**site is-relay-node**

**site relay-nodes**

### 8.37.3. OPTIONS

**-c, --cache='CACHE\_NAME'**

Specifies a cache.

**-a, --all-caches**

Applies the command to all caches.

**-s, --site='SITE\_NAME'**

Specifies a backup location.

### 8.37.4. STATE TRANSFER MODE OPTIONS

**--mode='MODE'**

Sets the state transfer mode. Values are **MANUAL** (default) or **AUTO**.

### 8.37.5. EXAMPLES

`site status --cache=mycache`

Returns the status of all backup locations for **mycache**.

`site status --all-caches`

Returns the status of each backup location for all caches with backups.

`site status --cache=mycache --site=NYC`

Returns the status of **NYC** for **mycache**.

`site bring-online --cache=mycache --site=NYC`

Brings the site **NYC** online for **mycache**.

`site take-offline --cache=mycache --site=NYC`

Takes the site **NYC** offline for **mycache**.

`site push-site-state --cache=mycache --site=NYC`

Backs up caches to remote backup locations.

`site push-site-status --cache=mycache`

Displays the status of the operation to backup **mycache**.

`site cancel-push-state --cache=mycache --site=NYC`

Cancels the operation to backup **mycache** to **NYC**.

`site cancel-receive-state --cache=mycache --site=NYC`

Cancels the operation to receive state from **NYC**.

`site clear-push-state-status --cache=myCache`

Clears the status of the push state operation for **mycache**.

`site state-transfer-mode get --cache=myCache --site=NYC`

Retrieves the state transfer mode for **mycache** to **NYC**.

`site state-transfer-mode set --cache=myCache --site=NYC --mode=AUTO`

Configures automatic state transfer for `mycache` to `NYC`.

`site name`

Returns the name of the local site. If cross-site replication is not configured, the name of the local site is always "local".

`site view`

Returns a list of names for all sites or an empty list ("[]") if cross-site replication is not configured.

`site is-relay-node`

Returns true if the node handles RELAY messages between clusters.

`site relay-nodes`

Returns a list of relay nodes by their logical names.

## 8.38. STATS(1)

### 8.38.1. NAME

`stats` - displays statistics about resources.

### 8.38.2. SYNOPSIS

`stats` [`PATH`]

### 8.38.3. EXAMPLES

`stats //containers/default`

Displays statistics about the default container.

`stats //containers/default/caches/mycache`

Displays statistics about the `mycache` cache.

### 8.38.4. SEE ALSO

`cd(1)`, `ls(1)`, `describe(1)`

## 8.39. TASK(1)

### 8.39.1. NAME

`task` - executes and uploads server-side tasks and scripts

### 8.39.2. SYNOPSIS

`task upload --file='script' 'TASK_NAME'`

`task exec` [`TASK_NAME`]

### 8.39.3. EXAMPLES

```
task upload --file=hello.js hello
```

Uploads a script from a `hello.js` file and names it `hello`.

```
task exec @@cache@names
```

Runs a task that returns available cache names.

```
task exec hello -Pgreetee=world
```

Runs a script named `hello` and specifies the `greetee` parameter with a value of `world`.

### 8.39.4. OPTIONS

**-P, --parameters='PARAMETERS'**

Passes parameter values to tasks and scripts.

**-f, --file='FILE'**

Uploads script files with the given names.

### 8.39.5. SEE ALSO

ls(1)

## 8.40. UNALIAS(1)

### 8.40.1. NAME

unalias - deletes aliases.

### 8.40.2. SYNOPSIS

```
unalias 'ALIAS-NAME'
```

### 8.40.3. EXAMPLES

```
unalias q
```

Deletes the `q` alias.

### 8.40.4. SEE ALSO

config(1), alias(1)

## 8.41. USER(1)

### 8.41.1. NAME

user - manages `${infinispan.brand.name}` users in property security realms.

### 8.41.2. SYNOPSIS

**user ls**

**user create** 'username'

**user describe** 'username'

**user remove** 'username'

**user password** 'username'

**user groups** 'username'

**user encrypt-all**

**user roles ls** 'principal'

**user roles grant** --roles='role1'[, 'role2'...] 'principal'

**user roles deny** --roles='role1'[, 'role2'...] 'principal'

### 8.41.3. DESCRIPTION

Manage users in property realms with the **ls**, **create**, **describe**, **remove**, **password**, **groups** and **encrypt-all** subcommands. List and modify principal to role mappings with the **roles** subcommand when using the cluster role mapper for authorization.

### 8.41.4. COMMAND SYNOPSIS

**user ls**

Lists the users or groups which are present in the property file.

**user create** 'username'

Creates a user after prompting for a password.

**user describe** 'username'

Describes a user, including its username, realm and any groups it belongs to.

**user remove** 'username'

Removes the specified user from the property file.

**user password** 'username'

Changes the password for a user.

**user groups** 'username'

Sets the groups to which a user belongs.

**user encrypt-all**

Encrypt all passwords in a plain-text user property file.

### **user roles ls 'principal'**

Lists all roles of the specified principal (user or group).

### **user roles grant --roles='role1'[, 'role2'...] 'principal'**

Grants one or more roles to a principal.

### **user roles deny --roles='role1'[, 'role2'...] 'principal'**

Denies one or more roles to a principal.

## **8.41.5. COMMON OPTIONS**

These options apply to all commands:

### **-h, --help**

Displays a help page for the command or sub-command.

### **-s, --server-root='path-to-server-root'**

The path to the server root. Defaults to `server`.

### **-f, --users-file='users.properties'**

The name of the property file which contains the user passwords. Defaults to `users.properties`.

### **-w, --groups-file='groups.properties'**

The name of the property file which contains the user to groups mapping. Defaults to `groups.properties`.

## **8.41.6. USER CREATE/MODIFY OPTIONS**

### **-a, --algorithms**

Specifies the algorithms used to hash the password.

### **-g, --groups='group1,group2,...'**

Specifies the groups to which the user belongs.

### **-p, --password='password'**

Specifies the user's password.

### **-r, --realm='realm'**

Specifies the realm name.

### **--plain-text**

Whether passwords should be stored in plain-text (not recommended).

## **8.41.7. USER LS OPTIONS**

### **--groups**

Shows a list of groups instead of the users.

## 8.41.8. USER ENCRYPT-ALL OPTIONS

### **-a, --algorithms**

Specifies the algorithms used to hash the password.

## 8.42. VERSION(1)

### 8.42.1. NAME

version - displays the server version and CLI version.

### 8.42.2. SYNOPSIS

**version**

### 8.42.3. EXAMPLE

`version`

Returns the version for the server and the CLI.

### 8.42.4. SEE ALSO

`help(1)`